

## Mac:

### Firefox (Instructional Video)

1. Right click HTML launcher file (organtutor.html)
2. Select "open with" Firefox
3. Click on "Allow blocked content"
4. Check Flash player version (version is 21.0.0.242)
5. Open System Preferences
6. Click on Flash Player applet
7. Go to the Advanced tab
8. Click "Trusted Location Settings" -> "Add" -> "Add Folder"
9. Browse for "OrganTutor 3.0 Complete", click on the folder name once to select, then click "OK"-> "Confirm" -> "Close"
10. Close Flash player settings
11. Close Control Panel

### Chrome

1. Go to: [http://www.macromedia.com/support/documentation/en/flashplayer/help/settings\\_manager.html](http://www.macromedia.com/support/documentation/en/flashplayer/help/settings_manager.html)
2. Click one of the links under "TAB NAME/HELP PAGE". You should be prompted to allow Flash on [macromedia.com](http://www.macromedia.com).
3. Now, go to: [http://www.macromedia.com/support/documentation/en/flashplayer/help/settings\\_manager04.html](http://www.macromedia.com/support/documentation/en/flashplayer/help/settings_manager04.html). You'll see a flash widget that will let you add locations to the trusted sites. You can browse locations. For a Mac the path should start with <file:///>, followed by the path to the files. If the files are on a DVD, it will need to be the path to the DVD drive (like D:\ or E:\).

## PC:

### Internet Explorer & Firefox (Instructional Video)

1. Right click HTML launcher file (organtutor.html)
2. Select "open with" Firefox or Internet Explorer
3. Click on "Allow blocked content"
4. Check Flash player version (version is 21.0.0.242)
5. Open Control Panel (Right Click on MS logo, select "control panel")
6. Click on Flash Player applet
7. Go to the Advanced tab
8. Click "Trusted Location Settings" -> "Add" -> "Add Folder"
9. Browse for "OrganTutor 3.0 Complete", click on the folder name once to select, then click "OK" -> "Confirm" -> "Close"
10. Close Flash player settings
11. Close Control Panel

### Chrome

1. Go to: [http://www.macromedia.com/support/documentation/en/flashplayer/help/settings\\_manager.html](http://www.macromedia.com/support/documentation/en/flashplayer/help/settings_manager.html)
2. Click one of the links under "TAB NAME/HELP PAGE". You should be prompted to allow Flash on [macromedia.com](http://www.macromedia.com).
3. Now, go to: [http://www.macromedia.com/support/documentation/en/flashplayer/help/settings\\_manager04.html](http://www.macromedia.com/support/documentation/en/flashplayer/help/settings_manager04.html). You'll see a flash widget that will let you add locations to the trusted sites. You can browse locations. For a PC the path should start with the drive letter (C:\, for example). If the files are on a DVD, it will need to be the path to the DVD drive (like D:\ or E:\).